

Installing Jurik Tools for Ninja Trader

Ninja Trader version

Verify that your version of Ninja Trader is 6.0.1000.7 or higher. If you need to download the latest version, select the menu command Help > Download_Site.

Install the Jurik “UT” Toolset

1. Execute the Installer, JRS_UT.EXE. Select NinjaTrader. Leave password field blank if you do not yet have an installation password from Jurik Research. Installer will analyze your computer and give you a computer identification number. Write it down.
2. Get your access PASSWORD from Jurik Research Software. You can do so by e-mailing to nfs@nfsmith.net. Be sure to give your full name, mailing address and computer identification number. You will then be given a password.
3. Rerun the installer JRS_UT.EXE, this time entering the password when asked. The installer will place a DLL file in your Windows system32 folder, and place the Toolset (as .CS files) into one of these folders:

Documents and Settings \ {your name } \ My Documents \ NinjaTrader 6 \ bin \ Custom \ Indicator

Documents and Settings \ {your name } \ My Documents \ NinjaTrader 6.5 \ bin \ Custom \ Indicator

Activating the Jurik Indicator Set

Start Ninja Trader. Select the command Tools > Edit NinjaScript > Indicator and select any Jurik indicator. After the file opens, press the F5 key to compile its code. This will also compile all Jurik indicators. Close the file.

Displaying Jurik Indicators

Open up any chart and press *CTRL-I* to open the Indicator Window. Scroll down and double-click on any “Jurik” indicator. After modifying its parameters values, press the APPLY button. To close the window, press OK.

(asterisks ** means NijaScript Editor cannot open this indicator)

Jurik CCX custom	CCI smoothed by JMA
Jurik DMX	Basic DMX **
Jurik DMX custom	Basic DMX
Jurik JMA	Basic JMA **
Jurik JMA custom	Basic JMA
Jurik JMA double stoch	%K stochastic applied to another %K, smoothed with JMA
Jurik JMA DWMA crossover	JMA and double-WMA plotted on price
Jurik JMA DWMA MACD	JMA and double-WMA used to make a MACD
Jurik RSX	Basic RSX **
Jurik RSX custom	Basic RSX
Jurik RSX on JMA	Applies RSX to JMA of data series
Jurik RSX on RSX	Applies RSX to RSX of data series
Jurik VEL	Basic VEL **
Jurik VEL custom	Basic VEL
Jurik VEL on VEL	Applies VEL to VEL of data series

What to do when your PASSWORD becomes invalid

If you upgrade to a new computer, or significantly upgrade your existing computer (such as flash a new BIOS), try to reinstall Jurik’s “UT” Toolset. The installer will let you know if your current password is no longer valid. Also, if you want to run the “UT” toolset on additional computers, you will need additional passwords. For new or replacement passwords, call 323-258-4860